

**NAME**

dbclean - remove secondary data from ICD data base

**SYNOPSIS**

**dbclean** [-aelcfvV] [cell ...]

**PARAMETERS**

*cell*      Process the named cells.

**OPTIONS**

**-a**      Process all cells.  
**-e**      Process all specified cells except those that are in the "exp\_dat" file.  
**-l**      Process only the layout view.  
**-c**      Process only the circuit view.  
**-f**      Process only the floorplan view.  
**-v**      Verbose mode.  
**-V**      Verbose mode. Informs for the layout view which streams are removed.

**DESCRIPTION**

*Dbclean* is a program to remove redundant and/or derived streams from the database, to save space when the design is ready.

For the layout view, all streams except the box, info, mc, nor, annotations and term streams are removed.

For the circuit view, the streams sls and sls.o are removed.

For the floorplan view, no streams are currently removed.

Additionally, the following files are removed from the data base: exp\_dat.

**BUGS**

The list of streams to be removed should be specified in a customizable file somewhere in the system instead of being hard-coded in the program.

**AUTHOR**

N. van der Meijs

**SEE ALSO**

rmdb(1ICD).