

**NAME**

clambda - change lambda value of the ICD database

**SYNOPSIS**

**clambda** [lambda]

**DESCRIPTION**

*Clambda* changes the lambda value of a project database. You can use this program only in a project directory. It can be used to set the correct value of lambda (in microns) which specifies your database unit in the GDS outputfile.

You may only do this, if you had set an incorrect lambda value with the *mkpr* program, and was working in other user units.

Note that cell data in the ICD database is NOT changed, all cell descriptions are expressed in terms of lambda rather than microns.

*Clambda* prints the current lambda value, when no lambda value is specified on the command line.

**AUTHOR**

R. Paulussen

**FILES**

./dmrc

**SEE ALSO**

cgi(1ICD), cig(1ICD), mkpr(1ICD).